

[SICom] – Installation



Content

1	Installation	3
---	--------------------	---

1 Installation

Open an Internet Browser and navigate to:

<http://fanox.blob.core.windows.net/sicom/publish.htm>


Because ClickOnce is a Microsoft technology we recommend to use Microsoft Edge or Internet Explorer to install SICom.

The new Microsoft Edge Chromium browser doesn't provide native Support for ClickOnce. It will by default NOT work to launch a Smart Office ClickOnce install point link in Edge Chromium.

To enable ClickOnce support in Edge Chromium:

1. Enter `edge://flags` link in Edge Chromium browser.
2. Scroll down to ClickOnce Support setting and select 'Enable' from the dropdown list.
3. Restart the browser.

If you want use Firefox you can use one firefox add-ons for clickonce. In another case if you want use Chrome you have add one clickonce complement for google chrome.



Click on Install Button.

According to the version of the browser that is performing the installation is possible to display the following notices.




Click on Run Button.

If you have antivirus program you may see a dialog like this



You must accept the dialog or you will be rejecting the application, with what you will see a dialog like this



The clickonce applications type over W10 perhaps needs be accepted in windows SmartScreen. You should accept the next screen.



The first time you are installing SICom prerequisites were installed. They are installation packages offered by Microsoft.

When prerequisites are installed begins the installation of SICom.



Click on Install button.

When the installation has finished SICom is initialized.

